
## Remotely control Raspberry Pi (teamviewer)

#### On Pi:

wget http://download.teamviewer.com/download/linux/version\_11x/teamviewer-host\_armhf.deb
sudo apt-get -f install
sudo dpkg -i teamviewer-host\_armhf.deb
sudo apt-get install -f



## On your laptop:

Install teamviewer on their website

Enter your ID and Password on your laptop's teamviewer, then you can use your laptop to remotely control your Pi.

## **Import python libraries on Raspberry Pi**

sudo pip install python boto ## change boto to the libraries you want

## Raspberry Pi HAT data collection

```
message['device'] = device
message['environment'] = environment
jsonData = json.dumps(message)
#sleep(0.5)
```

## **Communication between Pis (Bluetooth)**

- 1. Get two machines running Raspbian. One will be the server and the other will be the client.
- 2. On both machines, install python-bluez. sudo apt-get install python-bluez
- 3. Find out the server's Bluetooth address (e.g. using "hcitool dev")
- 4. Pair the client and server using Bluetooth address

#### For client Pi:

```
bd_addr = "B8:27:EB:3F:84:11" # here need to modify. use hciconfig to get address
port = 1
sock=bluetooth.BluetoothSocket( bluetooth.RFCOMM )
sock.connect((bd_addr, port))
sock.send(cPickle.dumps(data)) ## because the matrix cannot be transmitted
directly, you need to use cPickle.dumps()
sock.close()
```

#### For server Pi:

```
server_sock=bluetooth.BluetoothSocket( bluetooth.RFCOMM )
port = 1
server_sock.bind(("",port))
server_sock.listen(1)
client_sock,address = server_sock.accept()
data = client_sock.recv(1)
data_all = pickle.loads(".join(total_data)) ## pickle.loads() can be used to restore
your data type
```

## **Connect to AWS dynamoDB:**

```
conn = boto.dynamodb.connect_to_region(
   'us-east-2',## the region of your account
   aws_access_key_id=",
   aws secret access key=")
```

You can find your access key and secret access key on the following website <a href="https://aws.amazon.com/blogs/security/wheres-my-secret-access-key/">https://aws.amazon.com/blogs/security/wheres-my-secret-access-key/</a>

```
1. Creat table:
message_table_schema = conn.create_schema(
    hash_key_name = 'environment',
    hash_key_proto_value =str,
    range_key_name = 'Trigger_A',
    range_key_proto_value =str, (str can be changed to int.....)
table = conn.create table(
    name=' Trigger_A',
    schema= message_table_schema,
    read units=1, # if your want to transmit a large number of data, making this
number larger will be better
    write_units=1, # if your want to transmit a large number of data, making this
number larger will be better
2. Write new data to dynamoDB
table = conn.get_table('Trigger_A')
item_data = {
    'Time': 1501727062.38, ##you can add anything you want
item = table.new table(
    hash key = 'roomA'
    range key = '1'
    attrs = item data
Item.put()
3. Get item from dynamodb
table = conn.get_table('Trigger_A')
item = table.get item(
         hash key='roomA',
         range_key='1',
    )
print item['Time']
>> 1501727062.38
```



#### Or you can also update your dynamodb table:

```
item['Time'] = 123
print item['Time']
>>123
```


#### Lambda

If you want to import another python libraries, follow the step on the following websit: <a href="https://github.com/vitolimandibhrata/aws-lambda-numpy">https://github.com/vitolimandibhrata/aws-lambda-numpy</a> If you only want to use numpy, you can just download all documents on the wedsite.

## 1. Get item from dynamodb

```
dynamo = boto3.resource('dynamodb')
table_S = dynamo.Table('SampleSize')
db_response_S = table_S.scan()
item_S = tuple(db_response_S['Items'])
###because the data stored in the table would be like this: {u'Count': 1, u'Items':
[{u'Test': u'1', u'Sample_size': u'200', u'Time': Decimal('1502218588.4'), u'PC':
u'PC1'}], you need to use tuple() to get each item in 'Items'
datanum = int(item_S[0]['Sample_size'])
print datanum
```





# 2. Store data to dynamodb:

```
'w_2':1,## you can add some item you want
}
)


w_1

w_2

0

1
```

## In my system:



# **Required python libraries:**

On sensor Pi:

import bluetooth

import os

import json

import cPickle

import numpy as np

from time import sleep

from sense\_hat import SenseHat

import time

import matplotlib.pylab as plt

import boto

import boto.dynamodb

On gateway Pi:

import bluetooth

from time import sleep

import csv

import json

import cPickle

import pickle

```
import numpy as np
import random
import os
import socket
import ssl
import json
from time import sleep
from sense_hat import SenseHat
#from boto.s3.connection import S3Connection
import boto
#from boto.s3.key import Key
from socket import gaierror
from ConfigParser import NoOptionError
import time
import boto.dynamodb
import select
import matplotlib.pylab as plt
```

# **Code for sensor Pi:**


sense = SenseHat() # must need this to drive your HAT

## LED:

sense.set\_pixels(creeper\_pixels\_1) # show LED

```
Get sample size from dynamodb:
conn = boto.dynamodb.connect_to_region(
    'us-east-2',
    aws_access_key_id=", # your key
    aws_secret_access_key=") # your key
table = conn.get_table('SampleSize')
### see if the table is updated
while True:
    item = table.get_item(
                   # Our hash key is 'forum'
                   hash key=", #your key
                   # Our range key is 'subject'
                   range_key=", #your key
                   # This has the
                   #attrs=item data
    if old_size_time != item['Time']:
         old size time = item['Time']
         break
###get new sample size from dynamodb
datanum = int(item['Sample size'])/2 # separate sample size to gateway &sensor
equally
feature = 3
data all = np.zeros((datanum,feature+1)) #[timestamp pressure humidity
temperature]
###use sense HAT to sense data
for i in range(datanum):
         #led
         sense.set pixels(creeper pixels 1)
         #led
         message = {}
         device = {}
         device['cpuTemperature'] = os.popen('vcgencmd
measure temp').readline().replace("temp=","").replace("'C\n","")
         environment = {}
```

```
temp = {}
         temp['basedOnHumidity'] = sense.get_temperature_from_humidity()
         temp['basedOnPressure'] = sense.get temperature from pressure()
         environment['humidity'] = sense.get_humidity()
         environment['pressure'] = sense.get pressure()
         environment['temperature'] = temp
         message['device'] = device
         message['environment'] = environment
         jsonData = json.dumps(message)
         tdataTime = time.time() #use this to record timestamp in anywhere if you
want
         data_all[i][0] = tdataTime
         data_all[i][1] = sense.get_pressure()
         data all[i][2] = sense.get humidity()
         data_all[i][3] = sense.get_temperature_from_humidity()
###
bd addr = "XX:XX:XX:XX:XX" # here need to modify. use holiconfig to get address
port = 1
sock=bluetooth.BluetoothSocket( bluetooth.RFCOMM )
sock.connect((bd addr, port))
sock.send(cPickle.dumps(data all)) # need to change data type to make the
transmission successful.
sock.close()
Code for gateway Pi:
Gateway Pi also need to get new sample size from dynamodb, all this part is same as
sensor Pi.
datanum = int(item['Sample size'])/2
feature = 3
designmatrix = np.zeros((datanum*2,feature))
Target = np.zeros((datanum*2,1))
#####initial w(beta)#####
w old = np.zeros((feature,1))
w_new = np.zeros((feature,1))
```



```
E_old = 0
E new = 0
delta_E = np.zeros((datanum*2,feature))
learning_rate = 0.001
###bluetooth_server###
server sock=bluetooth.BluetoothSocket(bluetooth.RFCOMM)
port = 1
server_sock.bind(("",port))
server_sock.listen(1)
try:
    client_sock,address = server_sock.accept()
    print "Accepted connection from ",address
    tStart_blue_recv = time.time()
    total data = []
    while True:
         data 1 = client sock.recv(1)
         if len(data 1) == 0: # if transmission finished, then break
              break
         total data.append(data 1)
except IOError:
    pass
except KeyboardInterrupt:
    print "Stopping..."
    stop_advertising(server_sock)
    sys.exit()
data all = pickle.loads(".join(total data)) # need to pickle the data because I used
cPickle.dumps() on my sensor Pi
client_sock.close()
server_sock.close()
```

The next part is using gateway Pi to collect data, all this part is the same as sensor

```
<u>Pi.</u>
### Gradient descent ###
while True:
     w_old = w_new
     for i in range(datanum*2):
           delta_E[i,:] = delta_E[i,:] + (Target[i][0] -
np.dot(np.matrix(designmatrix[i,:]),np.matrix(w_old)))*designmatrix[i,:]
          ###normalization##
          \#delta_E[i,:] = ((delta_E[i,:] - np.min(delta_E[i,:]))/(np.max(delta_E[i,:])-
np.min(delta_E[i,:])))*2-1
          #delta_E[i,:] = delta_E[i,:] - np.min(delta_E[i,:])
          #delta E[i,:] = delta E[i,:]/np.max(delta E[i,:])
     w_new = w_old + learning_rate*np.matrix(delta_E[i,:]/(datanum*2)).T
     print "beta_old = ", w_old
     print "beta_new = ", w_new
     E_old = E_new
     for i in range(datanum*2):
           E \text{ new} = E \text{ new} + (Target[i][0] -
np.dot(np.matrix(designmatrix[i,:]),np.matrix(w_new)))**2
          E new = E new/2
     if E new > E old:
          learning rate = learning rate/2
The following are the formulations of gradient descent:
 Gradient descent
 • Beta^{t+1} = Beta^t + \eta * \Delta E
 • Initial Beta = [0,0,0]
 • E = \frac{1}{2} * (Target - X * Beta)^2
 • \Delta E = \frac{\partial E}{\partial X} = (Target - X * Beta) * X
### Connect to dynamodb and do some interaction###
table = conn.get table('sensingdata A')
item = table.get_item(
          # Our hash key is 'forum'
          hash key='roomA',
          # Our range key is 'subject'
```

```
range_key='sensorA',

# This has the

#attrs=item_data
)

tStart_pi_lambda = time.time()
item['feature_A'] = float(w_new[0][0])
item['feature_B'] = float(w_new[1][0])
item['feature_C'] = float(w_new[2][0])
item['Comm_pi_pi'] = bluetooth_transmission_time
item['Compu_pi'] = Compu_pi_time
item.put()
tEnd_pi_lambda = time.time()
Comm_pi_lambda = tEnd_pi_lambda - tStart_pi_lambda
item['Comm_pi_lambda'] = Comm_pi_lambda
item['Time'] = tEnd_pi_lambda
item.put()
```


#### On Lambda:

- Click Services -> IAM -> Roles -> lambda\_dynamodb\_role -> create role policy -> policy generator -> select -> AWS Service (choose Amazon DynamoDB) -> Actions (all actions(\*)) -> Add statement -> Amazon Resource Name (ARN) (you can find this on your dynamodb table -> overview) -> Add statement -> next step
- 2. Click Services -> lambda -> Function -> Create function -> dynamodb-process-stream-python
- 3. At configure trigger, set the table which you want to use to trigger lambda (starting position choose latest)
- 4. At configure function, set you lambda function name.
- 5. You can directly design your code here but you can only use the default python libraries, or upload the zip which include your code and extra python libraries.



# **Code for lambda:**

First, click your lambda function -> configuration -> check the name of handler



Your .py need to be same name as the handler. (from above figure, I need to set the name of my python code as dynamo.py)

```
import json
import boto3
import numpy as np
import decimal
from decimal import *
import time
print('Loading function')
def lambda handler(event, context):
    tStart = time.time()
    ### get new sample size from dynamodb###
    dynamo = boto3.resource('dynamodb')
    table_S = dynamo.Table('SampleSize')
    db response S = table S.scan()
    item S = tuple(db response S['Items'])
    datanum = int(item_S[0]['Sample_size'])
    featurenum = 3
    collectornum = 2
    X = np.zeros((datanum,featurenum))
    y = np.zeros((datanum,1))
    betam = np.zeros((featurenum,collectornum))
    table_A = dynamo.Table('sensingdata_A')
```


```
table_B = dynamo.Table('sensingdata_B')
table_C = dynamo.Table('sensingdata_C')
db_response_A = table_A.scan()
item_A = tuple(db_response_A['Items'])
betam[0][0] = item_A[0]['feature_A']
betam[1][0] = item A[0]['feature B']
betam[2][0] = item_A[0]['feature_C']
db_response_B = table_B.scan()
item_B = tuple(db_response_B['Items'])
betam[0][1] = item_B[0]['feature_A']
betam[1][1] = item_B[0]['feature_B']
betam[2][1] = item_B[0]['feature_C']
db_response_C = table_C.scan()
item C = tuple(db response C['Items'])
for i in range(datanum):
    X[i][0] = item_C[i]['X_1']
    X[i][1] = item C[i]['X 2']
    X[i][2] = item_C[i]['X_3']
    y[i][0] = item_C[i]['Y']
data_bytes = item_C[1000]['data_bytes']
### store some result to dynamodb ###
table LC = dynamo.Table('latency C')
db response LC = table LC.scan()
item LC = tuple(db response LC['Items'])
Comm_pi_pi_A = item_A[0]['Comm_pi_pi']
Comm_pi_pi_B = item_B[0]['Comm_pi_pi']
Comm pi pi C = item LC[0]['Comm pi pi']
Comm_pi_lambda_A = item_A[0]['Comm_pi_lambda']
```

```
Comm_pi_lambda_B = item_B[0]['Comm_pi_lambda']
    Comm_pi_lambda_C = item_LC[0]['Comm_pi_lambda']
    Compu_pi_A = item_A[0]['Compu_pi']
    Compu_pi_B = item_B[0]['Compu_pi']
    Compu_pi_C = item_LC[0]['ExecTime']
    Comm_pi_pi = np.max([Comm_pi_pi_A,Comm_pi_pi_B,Comm_pi_pi_C])
    Comm_pi_lambda =
np.max([Comm_pi_lambda_A,Comm_pi_lambda_B,Comm_pi_lambda_C])
    Compu_pi = np.max([Compu_pi_A,Compu_pi_B,Compu_pi_C])
    ### combine feature algorithm ###
    def prox simplex(y):
         # projection onto simplex
         n = len(y)
         val = -np.sort(-y)
         suppt_v = np.cumsum(val) - np.arange(1, n+1, 1) * val
         k = np.sum(suppt v < 1)
         lam = (np.sum(val[0:k_act]) - 1.0) / k_act
         x = np.maximum(y-lam, 0.0)
         return x
    def combine(y, X, betam):
         K = betam.shape[1]
         w = np.ones((K,)) / K
         maxit = 1000
         tol = 1e-3
         Xb = np.dot(X, betam)
         #print Xb
         step = 1.0 / np.max(np.linalg.svd(Xb, full matrices=0, compute uv=0)) ** 2
         for it in range(maxit):
             prev w = np.copy(w)
             #print w
             res = y - np.dot(np.matrix(Xb),np.matrix(w).T)
             grad = -np.dot(np.matrix(Xb).T,np.matrix(res))
             w -= step * np.squeeze(np.asarray(grad.T))
             w = prox\_simplex(w)
```

```
#print(w)
if np.linalg.norm(w - prev_w) / (1e-20 + np.linalg.norm(prev_w)) < tol:
    break</pre>
```

return w

#### ###The following figure shows you the concept of combining features:###



```
w = combine(y,X,betam)
    w_temp = [decimal.Decimal(str(w[i]))for i in range(collectornum)]
    wb = np.dot(np.matrix(betam),np.matrix(w).T)
    Predict_y = np.dot(np.matrix(X),wb)
    Predict y array = np.squeeze(np.asarray(Predict y))
    Predict_y_temp = decimal.Decimal(str(Predict_y_array[199]))
    ### need to change the type of the data to successfully store the data in to
dynamodb ###
    MSE = np.sqrt(np.sum((y-np.squeeze(np.asarray(Predict y)))**2))/datanum
    MSE temp = decimal.Decimal(str(MSE))
    tEnd = time.time()
    Lambda ExecTime = tEnd - tStart
    tEnd temp = decimal.Decimal(str(tEnd))
    Lambda ExecTime temp = decimal.Decimal(str(Lambda_ExecTime))
    table = dynamo.Table('weightresult')
    #print Predict y
    item = table.put item(
         Item = {
              'environment': 'roomA',
              'sensor': 'sensorA&B&C',
              'w 1': w temp[0],
              'w_2': w_temp[1],
```

```
'Prediction': Predict_y_temp,
             #'Real_Result': y[199],
             'Error': MSE_temp,
             'Lambda_ExecTime': Lambda_ExecTime_temp,
             'Time': tEnd_temp,
              'Comm_pi_pi': Comm_pi_pi,
              'Comm_pi_lambda': Comm_pi_lambda,
             'Compu_pi': Compu_pi,
             }
    )
Plot result:
from time import sleep
import csv
import json
import cPickle
import numpy as np
import paho.mqtt.client as paho
import os
import socket
import ssl
import json
import boto
from ConfigParser import NoOptionError
import time
import boto.dynamodb
import matplotlib.pylab as plt
import math
###connect to AWS dynamoDB###
connflag = False
conn = boto.dynamodb.connect_to_region(
    'us-east-2',
    aws access key id='AKIAIALH5BDUW5WVA3FA',
    aws_secret_access_key='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')
```

```
def on_connect(client, userdata, flags, rc):
    global connflag
    connflag = True
    if rc==0:
         print ("Connection status: successful")
    elif rc==1:
         print ("Connection status: Connection refused")
##Bytes of data##
def utf8len(s):
    return len(s.encode('utf-8'))
#mqttc = paho.Client()
#mqttc.on_connect = on_connect
#awshost = "act744dbdaqsy.iot.us-east-2.amazonaws.com"
#awsport = 8883
##clientId = "MyRaspberryPi"
##thingName = "MyRaspberryPi"
#caPath = "D:\Princeton testbed\\Final\\deviceSDK\\root-CA.pem.crt"
#certPath = "D:\Princeton testbed\\Final\\deviceSDK\\9ad1cc85e6-
certificate.pem.crt"
#keyPath = "D:\Princeton testbed\\Final\\deviceSDK\\9ad1cc85e6-private.pem.key"
#mqttc.tls set(caPath, certfile=certPath, keyfile=keyPath,
cert reqs=ssl.CERT REQUIRED, tls version=ssl.PROTOCOL TLSv1 2, ciphers=None)
#mqttc.connect(awshost, awsport, keepalive=60)
#
#mqttc.loop start()
Time old = 0
###see if the tables are updated
while True:
    table_1 = conn.get_table('latency_C')
    table 2 = conn.get table('weightresult')
    table 4 = conn.get table('sensingdata C')
    while True:
```

```
item_2 = table_2.get_item(
    # Our hash key is 'forum'
    hash_key='roomA',
    # Our range key is 'subject'
    range_key='sensorA&B&C',
    # This has the
    #attrs=item_data
    )
if Time_old != item_2['Time']:
    Time_old = item_2['Time']
    break
else:
    Time_old = item_2['Time']
```

# \*\*\*The next step is getting items from table, just the same as Sensor Pi.

fig, axs =plt.subplots(3,1) # you can change the number of subplot in a figure window fig.set\_size\_inches(20,2) # you can change the table size if you want

```
###plot table###
latency_collabel=
["Data_Amount","Communication_Latency","Communication_Latency","Computatio
n_Latency","Computation_Latency","Total_Latency"]
latency_data = [["(Bytes)","Sensor_Pi->Gateway_Pi","Gateway_Pi-
>Lambda","Gateway_Pi","Lambda","(second)"],[data_bytes,Comm_pi_pi,Comm_pi_l
ambda,Compu_pi,Compu_lambda,Total_Latency],[" "," "," "," "," "," "]]

colors = ['gray','#DDDDFF','#DDDDFF','#FFD0DF','#FFD0DF','#FFD0DF','#FDFFD0']
axs[0].axis('tight')
axs[0].axis('off') #without axis
the_table_latency =
axs[0].table(cellText=latency_data,colLabels=latency_collabel,loc='center',colColours =colors)
the_table_latency.scale(1.3,1.5)
```